
## DØ High Voltage System Tutorial

#### J. Frederick Bartlett



#### **Outline**

- Introduction to the HV Hardware
- Control System Features
- Operator GUI Programs
- Diagnostic Guidelines




#### **Hardware**


- High Voltage VME crate
  - 6U size
  - Custom backplane
  - Additional voltage supplies
    - +5V Digital, +- 12V Analog, +-12 V Bulk
- Fermilab/BiRa 4877 module
  - Six modules per VME crate
  - 8 channels per module
  - 10 voltage generator pod types
  - Cockroft-Walton generator
  - Backplane trip links
  - Backplane module address encoding (geographical)

#### **Hardware**

- Reference
  - Bi Ra "Model VME 4877PS High Voltage Power Supply System Manual"





## **EPICS Components**






## **EPICS IOC Components**





# **EPICS High Voltage**Support

- Record support
  - hv single HV channel
  - hvtrip common trip group of HV channels
- Device support
  - Fermilab/Bi Ra 4877



## **EPICS** Record Support

- HV Record hv
  - High-level device interface
  - Sequential state machine model (limited implementation of UML Harel diagrams)
  - Optional fast and slow histories (not implemented)
  - Corrective ramp algorithm
- Trip record hvtrip (not implemented)
  - Forms trip groups at the record level



#### **HV** Record

- Purpose
  - Control and monitor an individual HV channel
  - Add high-level operations to a basic voltage generator
- Implemented as a sequential state machine with states, transitions, actions, and events
- Ramping to a target voltage is a software function



# HV Record - Database Fields

#### Readback

- Voltage
- Current
- State
- Voltage trip level


#### Setting

- Command
- Target voltage
- Current trip level
- Current ramp factor
- Ramp rate
- Setting tolerance





## **HV Record - Pod Types**

| Pod Name | Max Voltage | <b>Max Current</b> |
|----------|-------------|--------------------|
| P5.5KV1  | +5.5kV      | 2.3 mA             |
| M5.5KV1  | -5.5 kV     | 2.3 mA             |
| P5.5KV2  | +5.5 kV     | 1.0 mA             |
| M5.5KV2  | -5.5 kV     | 1.0 mA             |
| P5.5KV3  | +5.5 kV     | 0.1 MA             |
| M5.5KV3  | -5.5 kV     | 0.1 mA             |
| P3.5KV   | +3.5 kV     | 3.5 mA             |
| M3.5KV   | -3.5kV      | 3.5 mA             |
| P2.0KV   | +2.0 kV     | 3.2 mA             |
| M10V1    | -10 V       | 0.2 mA             |



# HV Record - State Diagram





# HV Record - Ramp Algorithm

- Set current trip to ramp value
  - Determined by current ramp factor field
- Compute average voltage
- Compute voltage step size and number of steps to reach target voltage
- Execute ramp steps
- Compute average voltage



# HV Record - Ramp Algorithm

- Compare abs(Vaverage Vtarget)
   with Vtolerance
  - less or equal Enter HOLDING state
  - greater Repeat ramp sequence
- If the number of ramp cycles exceeds the limit, enter the PAUSE state and set an alarm condition



#### Initialization Modes

#### Standard

- Output voltage set to zero
- Initial state is OFF


#### Alternative

- Output voltage unaltered
- Initial state is LOCKED
- Required by calorimeter




## **HV Record - Trips**

- Channel
  - Overvoltage
    - Trimpot setting
  - Overcurrent
    - Register setting
  - External
    - Backplane connection
- Module
  - Watchdog
    - Module access timeout
  - Interlock
    - **■** Front panel connector
  - External
    - Backplane connection



## HV Record - Planned Extensions

- Slow history buffer
  - Sample rate: ~ 0.05 Hz
  - Voltage, current, and state recorded in circular buffers
  - Low pass filter
- Fast history buffer
  - Sample rate: ~ 30-60 Hz
  - Voltage, current, and state recorded in circular buffers
  - Buffer update algorithm
    - After a trip the buffer continues to collect readings for a specified time period after which it is locked



## Operator GUI Programs

#### Utility display

 Monitor crate parameters (backplane voltages and temperature)

#### Detector display

- Monitor channel state for multiple crates
- Control state change for multiple crates

#### Crate display

- Monitor channel parameters for a single crate
- Control state change for single channel or all channels



## **Operator GUI Programs**

- Product setup required for all displays
  - setup onl\_apps



## **Utility Display**


| <u>F</u> ile |       |            |           |            |          |          | <u>H</u> elp |  |  |
|--------------|-------|------------|-----------|------------|----------|----------|--------------|--|--|
| CAL          | FPD   | FPD LUM MU |           | SMT        |          |          |              |  |  |
| Crate        | +5 Di | gital +    | 12 Analog | -12 Analog | +12 Bulk | -12 Bulk | Temp DegC    |  |  |
|              | Pixel |            |           |            |          |          |              |  |  |
| M217C        | 5.0   | 7          | 12.31     | -12.18     | 12.28    | -12.37   | 23.36        |  |  |
| M217D        | 5.1   | 2          | 12.26     | -12.54     | 12.23    | -12.13   | 24.63        |  |  |
| M217E        | 5.1   | 0          | 12.18     | -12.36     | 12.23    | -12.09   | 21.73        |  |  |
| M218C        | 5.3   | 31         | 12.16     | -12.33     | 12.28    | -11.97   | 29.39        |  |  |
| M218D        | 5.1   | 5          | 12.18     | -12.21     | 12.25    | -11.97   | 29.89        |  |  |
| M218E        | 5.1   | 2          | 12.29     | -12.38     | 12.23    | -11.96   | 25.88        |  |  |
|              |       |            |           | Central    |          |          |              |  |  |
| M215B        | 5.0   | )5         | 12.27     | -12.50     | 12.21    | -12.50   | 24.46        |  |  |
| M215C        | 5.0   | 3          | 12.39     | -12.21     | 12.09    | -12.11   | 22.02        |  |  |
| M215D        | 5.0   | )5         | 12.31     | -12.24     | 12.43    | -12.61   | 20.26        |  |  |
| M215E        | 5.1   | 1          | 12.24     | -12.21     | 12.25    | -12.32   | 22.08        |  |  |
| M217B        | 5.0   | 3          | 12.27     | -12.15     | 12.34    | -12.30   | 25.19        |  |  |
| M218B        | 4.9   | 95         | 12.34     | -12.33     | 12.33    | -12.37   | 23.38        |  |  |
| Status:      |       |            |           |            |          |          |              |  |  |
| tatus:       |       |            |           |            |          |          |              |  |  |



## **Utility Display**

- Purpose
  - Monitor HV crate parameters
    - Backplane voltages
    - Temperature
- Properties
  - Organized by page
  - Read-only access
- Implementation
  - Python script
  - Program name HvuGui.py
  - Configuration scripts xxx.hvu
- Self executing file
  - /online/config/ctl/mch.hvu







#### Purpose

- Monitor state of channels in multiple crates
- Execute multiple-crate actions
- Initiate crate display

#### Properties


- Organized by crate
- Multi-crate action buttons

#### Implementation


- Python script
- Program name hv\_det.py
- Configuration script xxx.hvd




- Crate button
  - Start crate display
- Action buttons
  - SET HV set to a target voltage
  - RESET reset tripped channels
  - ON set channels to ON state
  - RAMP ramp channels to target voltage
  - PAUSE pause ramp
  - RESUME resume ramp
  - OFF set channels to OFF state



- Channel state colors
  - Black/Red OFFLINE,
     DISABLED, TRIPPED
  - Blue OFF
  - Green HOLDING, LOCKED
  - Orange ON
  - Yellow AVERAGE, RAMP, PAUSED



| X pcn / Tue    | Mar 20 15:1: | 2:05   |       |       |        |        | _ 🗆 ×    |
|----------------|--------------|--------|-------|-------|--------|--------|----------|
| Set HV         | RESET        | ON     | RAMP  | PAUSE | RESUME | OFF    | Quit     |
| <br><b>⋄</b> 0 | V_trip       | l_trip | V_max | V_set | V_read | I_read | Control  |
| <b>10%</b>     | -1700        | 2500   | -1620 | -1620 | -0.3   | -0.3   | Off      |
| ^ 20%<br>^ 30% | -1701        | 2500   | -1640 | -1640 | -1.1   | 0.8    | Off      |
| <b>40%</b>     | -1769        | 2500   | -1660 | -1660 | -0.1   | 0.0    | Off      |
| <b>♦ 50%</b>   | -1789        | 2500   | -1710 | -1710 | 0.6    | 0.6    | Disabled |
| ↑ 60%<br>↑ 70% | -1789        | 2500   | -1710 | -1710 | -1.0   | 1.3    | Off      |
| ◆ 80%          | -1788        | 2500   | -1680 | -1680 | 0.4    | -0.4   | Off      |
| <b>^</b> 90%   | -1695        | 2500   | -1620 | -1620 | -0.0   | 0.7    | Off      |
| <b>100%</b>    | -1691        | 2500   | -1640 | -1640 | -0.0   | 0.1    | Off      |
| PCN09          | -1792        | 2500   | -1660 | -1660 | 0.3    | 0.2    | Off      |
| PCN10          | -1700        | 2500   | -1640 | -1640 | 0.5    | 0.5    | Off      |
| PCN11          | -1799        | 2500   | -1700 | -1700 | 0.1    | 1.5    | Off      |
| PCN12          | -1794        | 2500   | -1670 | -1670 | 0.1    | 0.8    | Off      |
| PCN13          | -1698        | 2500   | -1560 | -1560 | 0.2    | 0.3    | Off      |
| PCN14          | -1699        | 2500   | -1580 | -1580 | -1.5   | 1.5    | Off      |
| PCN15          | -1696        | 2500   | -1630 | -1630 | 0.9    | 0.2    | Off      |
| PCN16          | -1695        | 2500   | -1630 | -1630 | -0.2   | 0.6    | Off      |
| PCN17          | -1793        | 2500   | -1730 | -1730 | -0.4   | 1.7    | Off      |
| PCN18          | -1697        | 2500   | -1640 | -1640 | -1640  | 1076   | Holding  |
| PCN19          | -1697        | 2500   | -1570 | -1570 | -1569  | 1829   | Holding  |
| PCN20          | -1695        | 2500   | -1570 | -1570 | -1568  | 1830   | Holding  |
| PCN21          | -1700        | 2500   | -1570 | -1570 | -1571  | 1836   | Holding  |
| PCN22          | -1698        | 2500   | -1600 | -1600 | -1599  | 1871   | Holding  |
| PCN23          | -1788        | 2500   | -1720 | -1720 | -1719  | 1505   | Holding  |
| PCN24          | -1685        | 2500   | -1590 | -1590 | -1589  | 1387   | Holding  |
|                |              |        |       |       |        |        |          |




- Purpose
  - Monitor individual channels
    - State
    - Voltage and current readback
    - Target voltage
    - Voltage and current trip levels
  - Execute all-channel and individual channel actions
  - Set all-channel and individual channel target voltages
  - Usually organized by crate




#### Properties

- Organized by channel
- Multi-channel action buttons
- Channel action menu button
- Implementation
  - Python script
  - Program name hv\_crate.py
  - Configuration script xxx.hvc
- Action buttons
  - Same as Detector display
- Channel state colors
  - Same as Detector display




- Planned extensions
  - Paged GUI display format
  - Optional display of additional channel parameters
    - Ramp rate, scaling factor, ...
  - Time plot generation



- Channel is in DISABLED state
  - Missing module
  - Incorrect pod type in database
  - Module does not respond
- Module trips after transition from OFF to ON state
  - After a period with the power off, the channel may not be stable. Leave the power on for several hours, after which the channel may recover.
  - Bad module



- Module trips during ramp but has not exceeded either the voltage or current trip limit
  - After a period with the power off or the channel in the OFF state, the channel may not be stable. Leave the channel in the ON state at zero output for several hours, after which the channel may recover
  - Bad module



- Ramp does not converge to target voltage
  - Record tuning parameters set incorrectly
    - Call an expert for this
  - Bad module
- Current trip during ramp caused by capacitance charging
  - Reduce ramp rate
  - Increase current scaling factor parameter



- Output voltage is unstable (noise)
  - One of the bulk +-12V supply voltages is missing. Use the HV utility program to check

